



**Program Directory for
IBM Enterprise PL/I for z/OS**

V3.7.0

Program Number 5655-H31

for Use with
z/OS V1.7.0 or later

Document Date: October 2007

GI10-8426-11

Note!

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 29.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 1999, 2007. All rights reserved.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

1.0 Introduction	1
1.1 Enterprise PL/I Description	1
1.1.1 Full Function versus Alternate Function Offerings	4
1.2 Enterprise PL/I FMIDs	4
2.0 Program Materials	6
2.1 Basic Machine-Readable Material	6
2.2 Optional Machine-Readable Material	8
2.3 Program Publications	8
2.3.1 Basic Program Publications	8
2.3.2 Optional Program Publications	8
2.4 Program Source Materials	9
2.5 Publications Useful During Installation	9
3.0 Program Support	10
3.1 Program Services	10
3.2 Preventive Service Planning	10
3.3 Statement of Support Procedures	11
4.0 Program and Service Level Information	12
4.1 Program Level Information	12
4.2 Service Level Information	12
5.0 Installation Requirements and Considerations	13
5.1 Driving System Requirements	13
5.1.1 Machine Requirements	13
5.1.2 Programming Requirements	13
5.2 Target System Requirements	14
5.2.1 Machine Requirements	14
5.2.2 Programming Requirements	14
5.2.2.1 Installation Requisites	14
5.2.2.2 Operational Requisites	15
5.2.2.3 Toleration/Coexistence Requisites	17
5.2.2.4 Incompatibility (Negative) Requisites	17
5.2.3 DASD Storage Requirements	17
5.3 FMIDs Deleted	20
5.4 Special Considerations	20
6.0 Installation Instructions	21
6.1 Installing Enterprise PL/I	21
6.1.1 SMP/E Considerations for Installing Enterprise PL/I	21
6.1.2 SMP/E Options Subentry Values	21

6.1.3	Sample Jobs	21
6.1.4	Set up ISPF Editor Macro (Optional)	23
6.1.5	Allocate SMP/E CSI (Optional)	24
6.1.6	Perform SMP/E RECEIVE	24
6.1.7	Allocate SMP/E Target and Distribution Libraries	24
6.1.8	Allocate HFS or zFS Paths	24
6.1.9	Create DDDEF Entries	25
6.1.10	Perform SMP/E APPLY	25
6.1.11	Enable/Register the Debug Tool feature of Enterprise PL/I (Full Function Offering only)	26
6.1.12	Run the Installation Verification Program	27
6.1.13	Change the defaults for the compiler options (Optional)	27
6.1.14	Perform SMP/E ACCEPT	27
6.1.15	Install IBM Debug Tool for z/OS	28
6.1.16	Run REPORT CROSSZONE	28
6.2	Activating Enterprise PL/I	28
6.2.1	HFS or zFS Execution	28
7.0	Notices	29
7.1	Trademarks	30
	Reader's Comments	31

Figures

1.	Basic Material: Program Tape Full Function - US English	6
2.	Basic Material: Program Tape Full Function - Japanese	7
3.	Basic Material: Program Tape Alternate Function - US English	7
4.	Basic Material: Program Tape Alternate Function - Japanese	7
5.	Program File Content	7
6.	Basic Material: Unlicensed Publications	8
7.	Optional Material: Unlicensed Publications	8
8.	Optional Material: Unlicensed Publications - Debug Tool	9
9.	Publications Useful During Installation	9
10.	PSP Upgrade and Subset ID	10
11.	Component IDs	11
12.	Driving System Software Requirements	14
13.	Mandatory Installation Requisites	15
14.	Conditional Operational Requisites	15
15.	Total DASD Space Required by Enterprise PL/I	17
16.	Total DASD Space Required by Enterprise PL/I Alternate Function Offering	17
17.	Storage Requirements for Enterprise PL/I Target Libraries	19
18.	Enterprise PL/I HFS or zFS Paths	19

19.	Storage Requirements for Enterprise PL/I Distribution Libraries	19
20.	SMP/E Options Subentry Values	21
21.	Sample Installation Jobs	22

1.0 Introduction

This Program Directory is intended for the system programmer responsible for program installation and maintenance. It contains information concerning the material and procedures associated with the installation of IBM Enterprise PL/I for z/OS. This publication refers to IBM Enterprise PL/I for z/OS as Enterprise PL/I.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 6 identifies the basic and optional program materials and documentation for Enterprise PL/I.
- 3.0, “Program Support” on page 10 describes the IBM support available for Enterprise PL/I.
- 4.0, “Program and Service Level Information” on page 12 lists the APARs (program level) and PTFs (service level) incorporated into Enterprise PL/I.
- 5.0, “Installation Requirements and Considerations” on page 13 identifies the resources and considerations required for installing and using Enterprise PL/I.
- 6.0, “Installation Instructions” on page 21 provides detailed installation instructions for Enterprise PL/I. It also describes the procedures for activating the functions of Enterprise PL/I, or refers to appropriate publications.

Before installing Enterprise PL/I, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that were supplied with this program in softcopy form as well as this Program Directory and then keep them for future reference. Section 3.2, “Preventive Service Planning” on page 10 tells you how to find any updates to the information and procedures in this Program Directory.

Enterprise PL/I is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The Program Directory is provided in softcopy form on the CBPDO tape which is identical to the hardcopy form provided with your order. All service and HOLDDATA for Enterprise PL/I are included on the CBPDO tape.

Do not use this Program Directory if you are installing Enterprise PL/I with a SystemPac or ServerPac. When using these offerings, use the jobs and documentation supplied with the offering. This documentation may point you to specific sections of the Program Directory as required.

1.1 Enterprise PL/I Description

With IBM Enterprise PL/I for z/OS V3.7, you can leverage more than 30 years of IBM experience in application development to facilitate your new On Demand Business endeavors, helping you to integrate PL/I and Web-based business processes in Web services, XML, Java and PL/I applications. This compiler's interoperability lets you capitalize on existing IT investment while smoothly incorporating new, Web-based applications as part of your organizations infrastructure.

Enterprise PL/I is a leading-edge, IBM z/OS-based compiler that helps you create and maintain mission-critical, line-of-business PL/I applications you want to execute on your z/OS systems. It gives you access to IBM DB2, IBM CICS, and IBM IMS systems, and other data and transaction systems.

NEW IN V3.7

- Debugging improvements
- Performance improvements
- Usability enhancements
- Improvements to help application programmers diagnose errors
- Serviceability improvements

Debugging improvements:

- The TEST option has been enhanced so that users can choose to view the source in the listing and in the Debug Tool source window as that source would appear after a user-specified preprocessor had been run (or after all the preprocessors had been run)

Performance improvements:

- The BASR instruction will now be used instead of the BALR instruction
- UNPKU will be used to convert some PICTURE to WIDECHAR (rather than making a library call)
- The conversions of FIXED DEC with large precision to FLOAT will be inlined and speeded up by the use of FIXED BIN(63) as an intermediary
- The CHAR built-in when applied to CHAR expressions will now always be inlined
- The code generated for conversions of FIXED BIN(p,q) to unscaled FIXED DEC has been significantly improved

Usability enhancements:

- IEEE Decimal Floating Point is supported (requires z/OS V1.9 or later, and ARCH(7) hardware)
- The new MEMCONVERT built-in function will allow the user to convert arbitrary lengths of data between arbitrary code pages
- The new ONOFFSET built-in function will allow the user to have easy access to another piece of information formerly available only in the runtime error message or dump, namely the offset in the user procedure at which a condition was raised
- The new STACKADDR built-in function will return the address of the current dynamic save area (register 13 on z/OS) and will make it easier for users to write their own diagnostic code
- The length of the mnemonic field in the assembler listing will be increased to allow for better support of the new z/OS instructions that have long mnemonics
- More of the right margin will be used in the attributes, cross-reference and message listings
- The default for the CEESTART option has been changed to CEESTART(FIRST)

- The CODEPAGE option will now accept 1026 (the Turkish code page) and 1155 (the 1026 code page plus the Euro symbol)
- The new MAXNEST option allows the user to flag excessive nesting of BEGIN, DO, IF and PROC statements
- Under the new (and non-default) suboption NOELSEIF of the RULES option, the compiler will flag any ELSE statement that is immediately followed by an IF statement and suggest that it be rewritten as a SELECT statement
- Under the new (and non-default) suboption NOLAXSTG of the RULES option, the compiler will flag declares where a variable A is declared as BASED on ADDR(B) and STG(A) > STG(B) not only (as the compiler did before) when B is AUTOMATIC, BASED or STATIC with constant extents but now also when B is a parameter declared with constant extents
- The new QUOTE option will allow the user to specify alternate code points for the quote (") symbol since this symbol is not code-page invariant
- The new XML compiler option can be used to specify that the tags in the output of the XMLCHAR built-in function be either in all upper case or in the case in which they were declared
- For compilations that produce no messages, the compiler will now include a line saying "no compiler messages" where the compiler messages would have been listed
- The MACRO preprocessor will support a new suboption that will allow the user to specify whether it should process only %INCLUDE statements or whether it should process all macro statements
- The integrated SQL preprocessor will now generate DB2 precompiler style declares for all *LOB_FILE, *LOCATOR, ROWID, BINARY and VARBINARY SQL types, in addition to the BLOB, CLOB and DBCLOB SQL types already supported, when the LOB(DB2) SQL preprocessor option is selected

Improvements to help application programmers diagnose errors:

- The compiler will now flag the use of AUTO (and STATIC) variables as tables in TRANSLATE and VERIFY (since this can lead to poor performance)
- The compiler will now flag the use of a function to set the initial value in a DO loop (since this can lead to unexpected results)
- The compiler will now scan for duplicate WHEN values in SELECT statements even if " is specified as a WHEN value
- The compiler will now flag any %DECLARE that does specify any attributes, thus leading to easier detection of errors, such as the extraneous comma in the statement "%DCL A, CHAR, B FIXED;"
- The compiler will now flag any SUBSTR reference where the third argument is zero since while technically valid, this is almost certainly a coding error
- The compiler will now optionally flag storage overlay problems where the base variable is a parameter
- The compiler will now flag the specification of a scale factor in a FLOAT declaration since this is invalid and may point to a typo in the source where FLOAT was typed but FIXED was meant

- The compiler will now flag any bit prefix operand that does not have the BIT attribute (as it already did for bit infix operands)

Serviceability improvements:

- The compiler will now flag a CLOSE statement for a file if that statement occurs in an ENDFILE ON-block for that file (thus detecting a user error that is usually resolved only after a PMR has been opened)
- The compiler will now flag ON ERROR blocks not starting with ON ERROR SYSTEM; (thus making it less likely users will have ON ERROR blocks that go into "infinite" loops)

1.1.1 Full Function versus Alternate Function Offerings

With V3.7, the mainframe interactive debug tool in Debug Tool for z/OS V8 is offered with the Enterprise PL/I compiler in the Full Function offering. This debug tool is a common facility that supports:

- Enterprise COBOL for z/OS
- Enterprise PL/I for z/OS
- COBOL for OS/390 & VM
- COBOL for MVS & VM
- VisualAge PL/I for OS/390
- PL/I for MVS & VM
- z/OS C/C++ optional feature
- OS/390 C/C++ optional feature

Only one Full Function Offering is required for debugging applications written in any of these programming languages. An Alternate Function Offering is available for customers who want to receive the Enterprise PL/I for z/OS compiler but not the Debug Tool.

IBM Debug Tool for z/OS V8.1.0 is also offered as a separate product. For more information about the function offered in the Debug Tool, refer to Software Announcement 207-205, (RFA45774) dated September 18, 2007.

1.2 Enterprise PL/I FMIDs

Enterprise PL/I consists of the following FMIDs:

H270370
J270371

Enterprise PL/I Full Function Offering consists of the following FMIDs:

H270370

J270371
HADE810
JADE81J

This program directory describes the installation procedure for H270370 and J270371 only. To install HADE810, and JADE81J, see the Debug Tool program directory (G110-8761-01).

2.0 Program Materials

An IBM program is identified by a program number and feature numbers. The program number for Enterprise PL/I is 5655-H31 and the feature numbers are 5812, 5802, 5832, and 5822.

Basic Machine-Readable Materials are materials that are supplied under the base license and feature numbers, and are required for the use of the product. Optional Machine-Readable Materials are orderable under separate feature numbers, and are not required for the product to function.

The program announcement material describes the features supported by Enterprise PL/I. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is magnetic tape or downloadable files. It is installed using SMP/E, and is in SMP/E RELFILE format. See 6.0, "Installation Instructions" on page 21 for more information about how to install the program.

Figure 1 describes the physical tape for the Full Function - US English

NOTE!

If Enterprise PL/I was shipped to you in a CBPDO, you will need to reference the CBPDO Memo To Users Extension for the physical tape layout of the Basic Machine-Readable Materials.

Figure 1. Basic Material: Program Tape Full Function - US English

Medium	Feature Number	Physical Volume	External Label	VOLSER
3480 tape	5812	1 of 2	Enterprise PL/I	270370
		2 of 2	Debug Tool Base (see Note below)	ADE810

Note: You will also receive this cartridge with your order. The Program Directory for IBM Debug Tool for z/OS contains the installation instructions for the Debug Tool base feature.

Figure 2 describes the physical tape for the Full Function - Japanese

Figure 2. Basic Material: Program Tape Full Function - Japanese

Medium	Feature Number	Physical Volume	External Label	VOLSER
3480 tape	5802	1 of 2	Enterprise PL/I	270370
		2 of 2	Debug Tool Base (see Note below)	ADE810
		3 of 3	Debug Tool JPN (see Note below)	ADE81J

Note: You will also receive this cartridge with your order. The Program Directory for IBM Debug Tool for z/OS contains both the Debug Tool base and Japanese features.

Figure 3 describes the physical tape for the Alternate Function - US English

Figure 3. Basic Material: Program Tape Alternate Function - US English

Medium	Feature Number	Physical Volume	External Label	VOLSER
3480 tape	5832	1 of 1	Enterprise PL/I	270370

Figure 4 describes the physical tape for the Alternate Function - Japanese

Figure 4. Basic Material: Program Tape Alternate Function - Japanese

Medium	Feature Number	Physical Volume	External Label	VOLSER
3480 tape	5822	1 of 1	Enterprise PL/I	270370

Figure 5 describes the program file content for Enterprise PL/I. You can refer to the *CBPDO Memo To Users Extension* to see where the files reside on the tape.

Notes:

1. The data set attributes in this table should be used in the JCL of jobs reading the data sets, but since the data sets are in IEBCOPY unloaded format, their actual attributes may be different.
2. If any RELFILEs are identified as PDSEs, ensure that SMPTLIB data sets are allocated as PDSEs.

Figure 5 (Page 1 of 2). Program File Content

Name	ORG	RECFM	LRCL	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.H270370.F1	PDS	FB	80	8800
IBM.H270370.F2	PDSE	U	0	6144

Figure 5 (Page 2 of 2). Program File Content

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.J270371.F1	PDS	VB	255	27998

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for Enterprise PL/I.

2.3 Program Publications

The following sections identify the basic and optional publications for Enterprise PL/I.

2.3.1 Basic Program Publications

Figure 6 identifies the basic unlicensed program publications for Enterprise PL/I. One copy of each of these publications is included when you order the basic materials for Enterprise PL/I. For additional copies, contact your IBM representative.

Figure 6. Basic Material: Unlicensed Publications

Publication Title	Form Number
Enterprise PL/I for z/OS License Information	GC27-1455

2.3.2 Optional Program Publications

Figure 7 identifies the optional unlicensed program publications for Enterprise PL/I. These publications are available free of charge in displayable softcopy format (BookManager and PDF) from the Enterprise PL/I Web site at <http://www.ibm.com/software/awdtools/pli/plizos/>

Figure 7 (Page 1 of 2). Optional Material: Unlicensed Publications

Publication Title	Form Number
Programming Guide	SC27-1457
Migration Guide	GC27-1458
Language Reference	SC27-1460

<i>Figure 7 (Page 2 of 2). Optional Material: Unlicensed Publications</i>	
Publication Title	Form Number
Messages and Codes	SC27-1461
Data Sheet	G224-7284

Figure 8 identifies optional unlicensed program publications for Debug Tool. These publications are available free of charge in displayable softcopy format (BookManager and PDF) from the Debug Tool Web site at <http://www.ibm.com/software/awdtools/debugtool/library/>.

<i>Figure 8. Optional Material: Unlicensed Publications - Debug Tool</i>	
Publication Title	Form Number
Customization Guide	SC19-1200
Reference and Messages	GC19-1198
Reference Summary	SC19-1199
User's Guide	SC19-1196

2.4 Program Source Materials

No program source materials or viewable program listings are provided for Enterprise PL/I.

2.5 Publications Useful During Installation

The publications listed in Figure 9 may be useful during the installation of Enterprise PL/I. To order copies, contact your IBM representative or visit the IBM Publications Center on the World Wide Web at: <http://www.ibm.com/shop/publications/order>

<i>Figure 9. Publications Useful During Installation</i>	
Publication Title	Form Number
<i>IBM SMP/E for z/OS User's Guide</i>	SA22-7773
<i>IBM SMP/E for z/OS Commands</i>	SA22-7771
<i>IBM SMP/E for z/OS Reference</i>	SA22-7772
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA22-7770

3.0 Program Support

This section describes the IBM support available for Enterprise PL/I.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before installing Enterprise PL/I, it is VERY IMPORTANT that you review the current Preventive Service Planning (PSP) information. The PSP buckets maintain current lists (which have been identified since the package was created) of any recommended or required service for this package's installation. This includes software PSP information that contains HIPER, and/or required PTFs against the base release.

While there can be overlap between software, hardware, and functional PSP buckets, reviewing all that apply to this package will ensure that you identify any known service required for your installation of this package.

If you obtained Enterprise PL/I as part of a CBPDO, there is HOLDDATA included on the PDO.

If the CBPDO for Enterprise PL/I is more than two weeks old when you install it, you should contact the IBM Support Center, use S/390 SoftwareXcel to obtain the current "PSP Bucket" or obtain the current PSP from the Web at <https://techsupport.services.ibm.com/server/390.psp390>

For program support, access the Software Support Web site at <http://www-3.ibm.com/software/support/>

PSP Buckets are identified by UPGRADEs, which specify product levels, and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for Enterprise PL/I are:

Figure 10. PSP Upgrade and Subset ID

UPGRADE	SUBSET	Description
PLIENT370	H270370	Enterprise PL/I Base
	J270371	Enterprise PL/I HFS
DEBUG810	HADE810	Debug Tool Base
	JADE81J	Debug Tool JPN

3.3 Statement of Support Procedures

Report any difficulties you have using this program to your IBM Support Center. If an APAR is required, the Support Center will advise how you should submit any needed information or documentation.

Figure 11 on page 11 identifies the component IDs (COMPID) for Enterprise PL/I.

<i>Figure 11. Component IDs</i>			
FMID	COMPID	Component Name	RETAIN Release
H270370	5655H3100	Enterprise PL/I Base	370
J270371	5655H3100	Enterprise PL/I HFS	371
HADE810	5655S1700	Debug Tool Base	810
JADE81J	5655S1700	Debug Tool JPN	81J

4.0 Program and Service Level Information

This section identifies the program and any relevant service levels of Enterprise PL/I. The program level refers to the APAR fixes incorporated into the program. The service level refers to the PTFs incorporated into the program.

4.1 Program Level Information

The following APAR fixes against previous releases of Enterprise PL/I have been incorporated into this release. They are listed by FMID.

- FMID H270360

PK31085	PK37382	PK42590	PK47492
PK33573	PK37831	PK42987	PK47781
PK34048	PK37911	PK43298	PK47832
PK34534	PK38512	PK43479	PK48370
PK34968	PK38609	PK43760	PK48461
PK34974	PK38690	PK44278	PK48590
PK35194	PK38964	PK44370	PK48907
PK35230	PK39389	PK44846	PK49464
PK35232	PK39811	PK44951	PK49536
PK35567	PK39939	PK45684	PK50150
PK35693	PK39946	PK45741	PK50227
PK35865	PK40152	PK45844	PK50320
PK35889	PK40399	PK45978	PK50707
PK36219	PK40671	PK46411	PK51727
PK36736	PK41330	PK46467	PK51901
PK36855	PK41987	PK46580	PK52213
PK37370	PK42365	PK46997	

4.2 Service Level Information

No PTFs against this release of Enterprise PL/I have been incorporated into the product tape.

Over time it is HIGHLY recommended that you frequently check the Enterprise PL/I PSP bucket for HIPER and SPECIAL Attention PTFs against all FMIDs which should be installed.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating Enterprise PL/I. The following terminology is used:

- *Driving system*: the system used to install the program.

The program may have specific operating system or product level requirements for utilizing processes such as binder or assembly utilities during the install.

- *Target system*: the system on which the program is intended to run.

The program may have specific product level requirements such as needing access to another product's library for link-edits that may directly affect the elements during the install or for its basic or enhanced operation. These requirements may be mandatory or optional.

In many cases, the same system can be used as both a driving system and a target system. However, you may want to set up a clone of your system to use as a target system by making a separate IPL-able copy of the running system. The clone should include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Some cases where two systems should be used include the following:

- When installing a new level of a product that is already installed, the new product will delete the old one. By installing onto a separate target system, you can test the new product while still keeping the old one in production.
- When installing a product that shares libraries or load modules with other products, the installation can disrupt the other products. Installing onto a test system or clone will allow you to assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install Enterprise PL/I.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 12. Driving System Software Requirements

Program Number	Product Name and Minimum VRM/Service Level
Any one of the following:	
5694-A01	z/OS V1.7.0 or later
5655-G44	SMP/E for z/OS V3.3.0 or later

Enterprise PL/I is installed into a file system, either HFS or zFS. Before installing Enterprise PL/I, you must ensure that the target system HFS or zFS data sets are available for processing on the driving system. OMVS must be active on the driving system and the target system HFS or zFS data sets must be mounted on the driving system.

If you plan to install Enterprise PL/I in a zFS file system, this requires that zFS be active on the driving system. Information on activating and using zFS can be found in z/OS Distributed File Service zSeries File System Administration, SC24-5989.

5.2 Target System Requirements

This section describes the environment of the target system required to install and use Enterprise PL/I.

Enterprise PL/I installs in the z/OS (Z038) SREL.

5.2.1 Machine Requirements

IBM Enterprise PL/I for z/OS V3.7 will run only on the following (and follow-on) hardware models:

- 9672-xx6 (G5)
- 9672-xx7 (G6)

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites: An installation requisite is defined as a product that is required and **must** be present or one that is not required but **should** be present on the system for the successful installation of this product.

A mandatory installation requisite identifies products that are required, without exception, or this product **will not install** on your system. This includes products specified as PREs or REQs.

Figure 13. Mandatory Installation Requisites

Program Number	Product Name and Minimum VRM/Service Level
5694-A01	z/OS V1.7.0 or later

A conditional installation requisite identifies products that are **not** required for successful install but may resolve such things as certain warning messages at installation time. They include products that are specified as IF REQs.

Enterprise PL/I has no conditional installation requisites.

5.2.2.2 Operational Requisites: An operational requisite is defined as a product that is required and **must** be present or a product that is not required but **should** be present on the system in order for this product to operate all or some of its functions.

A mandatory operational requisite identifies products that are required, without exception, or this product **will not operate** its basic function unless the requisite is met. This includes products specified as PREs or REQs.

Enterprise PL/I has no mandatory operational requisites.

A conditional operational requisite identifies products that are **not required** for the basic function but are needed at run time for this product to utilize specific functions. They may include products specified as IF REQs.

Figure 14 (Page 1 of 2). Conditional Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level	Function
5655-G53	Enterprise COBOL for z/OS and OS/390 V3	Interlanguage communication with COBOL
5696-234	High Level Assembler for MVS & VM & VSE	Interlanguage communication with assembler
5688-235	PL/I for MVS & VM V1.1.1	Interlanguage communication with PL/I
5668-909, 5668-910, 5668-911	OS PL/I V2.3	PL/I source programs (for interlanguage communication)
5668-806, 5688-087	VS Fortran V2.1.0	Interlanguage communication with Fortran
Any one of the following:		
5655-147	CICS Transaction Server for OS/390, V1	CICS applications
5697-E93	CICS Transaction Server for z/OS, V2	CICS applications

Figure 14 (Page 2 of 2). Conditional Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level	Function
5655-M15	CICS Transaction Server for z/OS, V3	CICS applications
Any one of the following:		
5688-197	COBOL for MVS & VM V1.2.0	Interlanguage communication with COBOL
5648-A25	COBOL for OS/390 & VM V2.1.0	Interlanguage communication with COBOL
Any one of the following:		
5675-DB2	DB2 Universal Database for z/OS and OS/390, V7	DB2 integrated coprocessor
5625-DB2	DB2 Universal Database for z/OS, V8	DB2 integrated coprocessor
5635-DB2	DB2 Universal Database for z/OS, V9	DB2 integrated coprocessor
Any one of the following:		
5655-M18	Debug Tool for z/OS V5.1.0	Application debugging support
5655-P14	Debug Tool for z/OS V6.1.0	Application debugging support
5655-R44	Debug Tool for z/OS V7.1.0	Application debugging support
5655-S17	Debug Tool for z/OS V8.1.0	Application debugging support
Any one of the following:		
5655-M19	Debug Tool Utilities and Advanced Functions for z/OS V5.1.0	Advanced application debugging support
5655-P15	Debug Tool Utilities and Advanced Functions for z/OS V6.1.0	Advanced application debugging support
5655-R45	Debug Tool Utilities and Advanced Functions for z/OS V7.1.0	Advanced application debugging support
5655-S16	Debug Tool Utilities and Advanced Functions for z/OS V8.1.0	Advanced application debugging support
Any one of the following:		
5655-B01	IMS V7	IMS applications
5655-C56	IMS V8	IMS applications
5655-J38	IMS V9	IMS applications
5635-A01	IMS V10	IMS applications
Any one of the following:		
5694-A01	DFSORT element of z/OS	Sort support
5647-A01	DFSORT element of OS/390	Sort support

5.2.2.3 Toleration/Coexistence Requisites: A toleration/coexistence requisite is defined as a product that must be present on a sharing system. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD at different time intervals.

Enterprise PL/I has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites: A negative requisite identifies products that must *not* be installed on the same system as this product.

Enterprise PL/I has no negative requisites.

5.2.3 DASD Storage Requirements

Enterprise PL/I libraries can reside on all supported DASD types. The values below are for 3390 DASD.

Figure 15 lists the total space required for each type of library.

<i>Figure 15. Total DASD Space Required by Enterprise PL/I</i>	
Library Type	Total Space Required in 3390 Trks
Target	1284 Tracks
Distribution	1385 Tracks
HFS	15 Tracks

<i>Figure 16. Total DASD Space Required by Enterprise PL/I Alternate Function Offering</i>	
Library Type	Total Space Required
Target	718 Tracks
Distribution	798 Tracks
HFS	15 Tracks

Notes:

1. IBM recommends use of system determined block sizes for efficient DASD utilization for all non-RECFM U data sets. For RECFM U data sets, IBM recommends a block size of 32760, which is the most efficient from a performance and DASD utilization perspective.
2. Abbreviations used for the data set type are:
 - U** Unique data set, allocated by this product and used only by this product. To determine the correct storage needed for this data set, this table provides all required information; no other tables (or Program Directories) need to be referenced for the data set size.

- S** Shared data set, allocated by this product and used by this product and others. To determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other Program Directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and others. This data set is NOT allocated by this product. To determine the correct storage needed for this data set, the storage size given in this table needs to be added to other tables (perhaps in other program directories). This existing data set must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old one and reclaim the space used by the old release and any service that had been installed. You can determine whether or not these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information on the names and sizes of the required data sets, please refer to 6.1.7, "Allocate SMP/E Target and Distribution Libraries" on page 24.

3. Abbreviations used for the HFS or zFS Path type are:

- N** New path, created by this product.
- X** Path created by this product, but may already exist from a previous release.
- P** Previously existing path, created by another product.

4. All target and distribution libraries listed have the following attributes:

- The default name of the data set may be changed.
- The default block size of the data set may be changed.
- The data set may be merged with another data set that has equivalent characteristics.
- The data set may be either a PDS or a PDSE, except SIBMZCMP and AIBMZMOD, which must be PDSEs.

5. All target libraries listed have the following attributes:

- The data set may be SMS-managed.
- It is not required for the data set to be SMS-managed.
- It is not required for the data set to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types identified in the SMPMCS.

6. All target libraries listed which contain load modules have the following attributes:

- The data set can be placed in the LPA.
- It is not required for the data set to be in the LPA.
- The data set can be placed in the LNKLIST.
- It is not required for the data set to be APF-authorized.

7. Enterprise PL/I requires that the SMPLTS data set must be a PDSE. If your existing SMPLTS is a PDS, you will need to allocate a new PDSE and copy you existing SMPLTS into it and then change the SMPLTS DDDEF entry to indicate the new PDSE data set.

The following figures describe the target and distribution libraries and HFS or zFS paths required to install Enterprise PL/I. The storage requirements of Enterprise PL/I must be added to the storage required by other programs having data in the same library or path.

Note: The data in these tables should be used when determining which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 17. Storage Requirements for Enterprise PL/I Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SIBMZCMP	LMOD	ANY	U	PDSE	U	0	701	n/a
SIBMZPRC	PROC	ANY	U	PDS	FB	80	6	5
SIBMZSAM	SAMP	ANY	U	PDS	FB	80	11	5

Figure 18. Enterprise PL/I HFS or zFS Paths

DDNAME	T Y P E	Path Name
SIBMZHFS	X	/usr/lpp/pli/IBM/

Figure 19. Storage Requirements for Enterprise PL/I Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
AIBMZHFS	U	PDS	VB	255	30	5
AIBMZMOD	U	PDSE	U	0	751	n/a
AIBMZSRC	U	PDS	FB	80	17	5

5.3 FMIDs Deleted

Installing Enterprise PL/I may result in the deletion of other FMIDs. To see what FMIDs will be deleted, examine the ++VER statement in the product's SMPMCS.

If you do not wish to delete these FMIDs at this time, you must install Enterprise PL/I into separate SMP/E target and distribution zones.

Note: These FMIDs will not automatically be deleted from the Global Zone. Consult the SMP/E manuals for instructions on how to do this.

5.4 Special Considerations

Enterprise PL/I has no special considerations for the target system.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of Enterprise PL/I.

Please note the following:

- If you want to install Enterprise PL/I into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMP/CSI and the SMP/E control data sets.
- Sample jobs have been provided to help perform some or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries required for SMP/E execution have been defined in the appropriate zones.
- The SMP/E dialogs may be used instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing Enterprise PL/I

6.1.1 SMP/E Considerations for Installing Enterprise PL/I

This release of Enterprise PL/I is installed using the SMP/E RECEIVE, APPLY, and ACCEPT commands. The SMP/E dialogs may be used to accomplish the SMP/E installation steps.

6.1.2 SMP/E Options Subentry Values

The recommended values for some SMP/E CSI subentries are shown in Figure 20. Use of values lower than these may result in failures in the installation process. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. Refer to the SMP/E manuals for instructions on updating the global zone.

SUB-ENTRY	Value	Comment
DSSPACE	(300,150,250)	Space allocation for SMPTLIB data sets (3390 DASD tracks)
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

6.1.3 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install Enterprise PL/I:

Figure 21. Sample Installation Jobs

Job Name	Job Type	Description	RELFIL
IBMZWEDT	MACRO	ISPF Editor macro to aid users in making changes to the sample jobs (optional)	IBM.H270370.F1
IBMZWSMP	SMP/E	Sample job to define and prime a new SMP/E CSI (optional)	IBM.H270370.F1
IBMZWRCV	RECEIVE	Sample RECEIVE job for Enterprise PL/I	IBM.H270370.F1
IBMZWALO	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.H270370.F1
IBMISMKD	MKDIR	Sample job to invoke the supplied IBMMKDIR EXEC to allocate HFS paths	IBM.H270370.F1
IBMZWDDF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.H270370.F1
IBMZWAPL	APPLY	Sample APPLY job	IBM.H270370.F1
IBMZWIVP	IVP	Sample job to verify installation has been successful	IBM.H270370.F1
IBMZWIOP	IOP	Sample job to change default compiler options (optional)	IBM.H270370.F1
IBMZWACP	ACCEPT	Sample ACCEPT job	IBM.H270370.F1

You can access the sample installation jobs by performing an SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 21 on page 21 to find the appropriate relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.H270370.F1,UNIT=tunit,
// VOL=SER=volser,LABEL=(x,SL),
// DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.H270370.F1,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSN=jcl-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(10,2,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
SELECT MEMBER=(IBMZWSMP,IBMZWRCV,IBMZWEDT)
SELECT MEMBER=(IBMZWALO,IBMZWDDF,IBMZWACP)
```

```
SELECT MEMBER=(IBMISMKD, IBMZWAPL, IBMZWIVP)
SELECT MEMBER=(IBMZWIOP)
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.H270370.F1 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4 Set up ISPF Editor Macro (Optional)

To aid you in making changes to the SMP/E installation jobs (IBMISMKD, IBMZWACP, IBMZWALO, IBMZWAPL, IBMZWDDF, IBMZWIOP, IBMZWIVP, IBMZWRECV and IBMZWSMP), an ISPF editor macro called IBMZWEDT, is supplied, which is copied to your output data set **jcl-library-name** above. (See Figure 21 on page 21).

This macro lets you substitute proper values for all of the required variables in those jobs instead of having you make the changes repeatedly by hand.

Edit macro IBMZWEDT and provide the proper values. After making the changes, either copy IBMZWEDT to any data set in your TSO logon procedure SYSEXEC concatenation, or issue the commands below to make IBMZWEDT immediately accessible to your current ISPF session:

From ISPF option 6, issue:

```
ALLOCATE FI(SYSUEXEC) DA('jcl-library-name') SHR REU
ALTLIB ACTIVATE USER(EXEC)
```

Then edit your installation jobs from this ISPF session.

Consult the instructions in the macro for more information.

6.1.5 Allocate SMP/E CSI (Optional)

If you are using an existing CSI, do not execute this job.

If you are allocating a new SMP/E data set for this install, edit, and submit sample job IBMZWSMP to allocate the SMP/E data set for Enterprise PL/I.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.6 Perform SMP/E RECEIVE

Having obtained Enterprise PL/I as part of a CBPDO, use the RCVPDO job found in the CBPDO RIMLIB data set to RECEIVE the Enterprise PL/I FMIDs as well as any service, HOLDDATA, included on the CBPDO tape. For more information, refer to the documentation included with the CBPDO.

You can also choose to edit and submit sample job IBMZWRCV to perform the SMP/E RECEIVE for Enterprise PL/I. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.7 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job IBMZWALO to allocate the SMP/E target and distribution libraries for Enterprise PL/I. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.8 Allocate HFS or zFS Paths

The target system HFS or zFS data set must be mounted on the driving system when running the sample IBMISMKD job since the job will create paths in the HFS or zFS.

Before running the sample job to create the paths in the file system, you must ensure that OMVS is active on the driving system, and that the target system's HFS or zFS file system is mounted to the driving system. zFS must be active on the driving system if you are installing Enterprise PL/I into a file system that is zFS.

If you plan to install Enterprise PL/I into a new HFS or zFS file system, you must create the mountpoint and mount the new file system to the driving system. For Enterprise PL/I, the recommended mountpoint is: /usr/lpp/pli/IBM/

Edit and submit sample job IBMISMKD to allocate the HFS or zFS paths for Enterprise PL/I. Consult the instructions in the sample job for more information.

If you create a new HFS or zFS for this product, you should consider updating the BPXPRMxx PARMLIB member to mount the new file system at IPL time. This may be helpful if an IPL occurs before the installation is complete.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.9 Create DDDEF Entries

Edit and submit sample job IBMZWDDF to create DDDEF entries for the SMP/E target and distribution libraries for Enterprise PL/I. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.10 Perform SMP/E APPLY

1. Ensure you have the latest Enhanced HOLDDATA, then edit and submit sample job IBMZWAPL to perform an SMP/E APPLY CHECK for Enterprise PL/I. Consult the instructions in the sample job for more information.

Enhanced HOLDDATA introduces ERROR HOLDS against FMIDs for HIPER APARs. Prior to installing, you should ensure you have the latest Enhanced HOLDDATA (available at url <http://service.software.ibm.com/holdata/390holddata.html>). The FMID(s) should be installed regardless of the status of unresolved HIPERs, however, the software should not be deployed until the unresolved HIPERs have been analyzed to determine applicability.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the following on the APPLY CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of **ERRORS** and not of **WARNINGS** (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

There are two methods to complete an FMID installation where ++HOLDS for HIPERs exist for the FMID(s) being installed:

- a. To ensure that all recommended and critical service is installed with the FMID(s), add the SOURCEIDs of PRP, HIPER, and RSU* to the APPLY command. There may be PE or HIPER APARs that do not have resolving PTFs available yet. You need to analyze the symptom flags to determine if you want to BYPASS the specific ERROR HOLDS and continue the FMID installation.

```
APPLY S(fmid,fmid,...)
FORFMID(fmid,fmid,...)
SOURCEID(PRP,HIPER,RSU*,...)
GROUPEXTEND .
```

This method requires more initial research, but will provide resolution for all HIPERs that have fixes available and are not in a PE chain. There may still be unresolved PEs or HIPERs that will require the use of BYPASS.

- b. To install the FMID(s) as it would have been installed prior to Enhanced HOLDDATA, you can add a BYPASS(HOLDCLASS(HIPER)) operand to the APPLY command. This will allow the FMID to be installed even though there are HIPER ERROR HOLDS against it. Note that not all ERROR

HOLDS were bypassed, only the HIPER ERROR HOLDS. After the FMID(s) are installed, the SMP/E REPORT ERRSYSMODS command should be run to identify any missing HIPER maintenance.

```
APPLY S(fmid,fmid,...)
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER)) .
..any other parameters documented in the program directory
```

This method is the quicker of the two, but requires subsequent review of the REPORT ERRSYSMODS to investigate any HIPERs.

If you bypass any HOLDS during the installation of the FMID(s) because fixing PTFs were not yet available you can use the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink to be notified when the fixing PTF is available.

2. After you have taken any actions indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E apply all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 if this job runs correctly.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 if this job runs correctly.

6.1.11 Enable/Register the Debug Tool feature of Enterprise PL/I (Full Function Offering only)

Before running any applications with Debug Tool or the Installation Verification Program below, ensure that you enable/register the Debug Tool feature of Enterprise PL/I. To do this, include an entry for the Debug Tool feature of Enterprise PL/I in the IFAPRDxx parmlib member as follows:

```
PRODUCT OWNER('IBM CORP')
NAME('IBM ENT PL/I')
ID(5655-H31)
VERSION(*) RELEASE(*) MOD(*)
FEATURENAME('PL/I-DEBUG')
STATE(ENABLED)
```

Once you have updated IFAPRDxx, issue the SET PROD=xx operator command. Debug Tool will then be enabled in the z/OS environment.

6.1.12 Run the Installation Verification Program

Edit and submit sample job IBMZWIVP to verify that you have installed Enterprise PL/I correctly. Consult the instructions in the sample job for more information.

Consult the instructions in the sample job for the expected output from the GO step.

Expected Return Codes and Messages: You will get a return code of 0 if the job runs correctly.

6.1.13 Change the defaults for the compiler options (Optional)

If you want to change the supplied default compiler options, then edit and submit sample job IBMZWIOP. This job will let you specify options that will be applied before any other options, thus effectively changing the default options. This job will also let you specify options that will be applied after all other options, thus effectively changing the default options and preventing them from being overridden. Consult the instructions in the sample job for more information.

6.1.14 Perform SMP/E ACCEPT

Edit and submit sample job IBMZWACP to perform an SMP/E ACCEPT CHECK for Enterprise PL/I. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the following on the ACCEPT CHECK: PRE, ID, REQ, and IFREQ. This is because the SMP/E root cause analysis identifies the cause only of **ERRORS** and not of **WARNINGS** (SYSMODs that are bypassed are treated as warnings, not errors, by SMP/E).

Before using SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. This will cause entries produced from JCLIN to be saved in the distribution zone whenever a SYSMOD containing inline JCLIN is ACCEPTed. For more information on the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E manuals.

Once you have taken any actions indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accept all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

If PTFs containing replacement modules are being ACCEPTed, SMP/E ACCEPT processing will link-edit/bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder may issue messages documenting unresolved external references, resulting in a return code of 4 from the ACCEPT step. These messages can be ignored, because the distribution libraries are not executable and the unresolved external references will not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly.

6.1.15 Install IBM Debug Tool for z/OS

See the Debug Tool program directory (GI10-8761-01) for further instructions on how to install and activate IBM Debug Tool for z/OS. The installation of Debug Tool is only applicable to the Full Function Offering.

6.1.16 Run REPORT CROSSZONE

The SMP/E REPORT CROSSZONE command will identify requisites defined for products that have been installed in separate zones. This command will also create APPLY and ACCEPT commands in the SMPPUNCH data set that you can use to install those cross-zone requisites it identifies.

After you have installed Enterprise PL/I, it is recommended that you run REPORT CROSSZONE against the new or updated target and distribution zones. REPORT CROSSZONE requires a global zone with ZONEINDEX entries describing all the target and distribution libraries to be reported on.

For more information on REPORT CROSSZONE, see the SMP/E manuals.

6.2 Activating Enterprise PL/I

6.2.1 HFS or zFS Execution

If you choose to have the HFS or zFS in which you have installed Enterprise PL/I mounted in read-only mode during execution, then no further tasks are required to accomplish this.

Enterprise PL/I is fully operational once the SMP/E installation is complete. No further customization is required to activate this function.

7.0 Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

7.1 Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

BookManager	MVS
C/370	MVS/ESA
CBPDO	OS/390®
CICS	ProductPac
CICS/ESA	RACF
COBOL/370	RETAIN
DATABASE 2	S/370
DB2®	SOMobjects
DFSMS	SP
DFSMS/MVS	SQL/DS
DFSORT	System/390
IBM®	SystemPac®
IMS®	VM/ESA
IMS/ESA	z/OS®
Language Environment	

Reader's Comments

Program Directory for IBM Enterprise PL/I for z/OS, October 2007

You may use this form to comment about this document, its organization, or subject matter with the understanding that IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

For each of the topics below please indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, please circle N.

RATING SCALE					
very satisfied	<----->	very dissatisfied	not applicable		
1	2 3 4	5	N		

	Satisfaction					
Ease of product installation	1	2	3	4	5	N
Contents of Program Directory	1	2	3	4	5	N
Installation Verification Programs	1	2	3	4	5	N
Time to install the product	1	2	3	4	5	N
Readability and organization of Program Directory tasks	1	2	3	4	5	N
Necessity of all installation tasks	1	2	3	4	5	N
Accuracy of the definition of the installation tasks	1	2	3	4	5	N
Technical level of the installation tasks	1	2	3	4	5	N
Ease of getting the system into production after installation	1	2	3	4	5	N

How did you order this product?

- CBPDO
- CustomPac
- ServerPac
- Independent
- Other

Is this the first time your organization has installed this product?

- Yes
- No

Were the people who did the installation experienced with the installation of z/OS products?

- Yes

___ No

If yes, how many years? ___

If you have any comments to make about your ratings above, or any other aspect of the product installation, please list them below:

Please provide the following contact information:

Name and Job Title

Organization

Address

Telephone

Thank you for your participation.

Please send the completed form to (or give to your IBM representative who will forward it to the IBM Enterprise PL/I for z/OS Development group):

International Business Machines Corporation
Reader's Comments
Department DTX/E269
555 Bailey Avenue
San Jose, California
USA
95141-9989

E-Mail: comments@us.ibm.com



Printed in U.S.A.

G110-8426-11

